

**precisely**

**ACR/Summary and ACR/Detail**

**Installation Guide**

For Windows



## Notices



### Trademarks

Infogix, the Infogix logo, ACR, ACR/Detail, ACR/Summary, ACR/Workbench, ACR/Connector, Infogix Assure, Infogix Insight, ACR/Instream, ACR/File, Infogix ER, Infogix Perceive, Data3Sixty, and Data360 are registered trademarks of Precisely. Data3Sixty Analyze, Data3Sixty Govern, Data3Sixty DQ+, Data360 Analyze, Data360 Govern and Data360 DQ+ are trademarks of Precisely. Any other trademarks or registered trademarks are the property of their respective owners.

1700 District Ave Ste 300  
Burlington MA 01803-5231  
USA

[www.precisely.com](http://www.precisely.com)

Copyright 2010, 2022 Precisely

---

# Contents

## Chapter 1 Introduction

About This Guide .....	5
Contacting Customer Support .....	6

## Chapter 2 Installing ACR/Summary and ACR/Detail Server

System Requirements for the Server .....	7
Overview of Server and Client Installation and Setup Steps .....	7
Installing the Product .....	8
Increase the Maximum File Size (Optional).....	10
Setting Up Java and COBOL Environment (Optional).....	10
Licensing Key .....	11

## Chapter 3 Configuring and Licensing the Server

When You Do Not Have to Create a Logon Account .....	13
Creating a Logon Account .....	13
Starting the Service .....	15
Setting and Modifying Server Properties .....	17
Implementing and Maintaining Your Licensing .....	22
Upgrading from a Pre-Release 4.0 Release.....	30

## Chapter 4 Installing a Client

Before You Begin .....	31
System Requirements for a Client.....	31
Steps for Installing a Client.....	31

## Chapter 5 Installing and Licensing ACR/Workbench

System Requirements for ACR/Workbench .....	33
Overview of ACR/Workbench Installation and Setup Steps .....	33

## ■ Contents

---

Uninstall the Previous Release if Appropriate .....	33
Installing the Product .....	34
Installing the Licensing Key .....	34
Upgrading from ACR 4.7, 4.8, or 4.9 Release .....	35
Upgrading from a Pre-Release 4.0 Release.....	36
Setting Up Java and COBOL Environment (Optional).....	36
Using ACR/Workbench .....	37
<b>Chapter 6    Upgrading from a Pre-Release 4.0 Release</b>	
Upgrading ACR/Summary for Windows .....	39
Upgrading ACR/Detail for Windows.....	43
<b>Index .....</b>	<b>47</b>

---

## Introduction

This chapter provides an overview to this guide and includes the following sections:

- “About This Guide” on page 5
- “Contacting Customer Support” on page 6

## About This Guide

This guide provides installation and licensing instructions for the following products

- ACR/Summary and ACR/Detail Server and Clients.
- ACR/Workbench.

## Audience

This guide is intended for the person who will install and/or upgrade the products listed above.

## Organization of Information

Chapter 1, “Introduction” describes the components of the guide and provides information for contacting Customer Support.

Chapter 2, “Installing ACR/Summary and ACR/Detail Server” includes system requirements and instructions for installing the Server and, for first-time installations, installing the Net Express licensing key.

Chapter 3, “Configuring and Licensing the Server” explains how to configure the server and how to activate and maintain your licensing.

Chapter 4, “Installing a Client” includes system requirements and instructions for installing ACR/Summary Client or ACR/Detail Client.

Chapter 5, “Installing and Licensing ACR/Workbench” provides system requirements and instructions for installing and licensing ACR/Workbench.

Chapter 6, “Upgrading from a Pre-Release 4.0 Release” provides instructions for upgrading ACR/Summary and ACR/Detail Server and ACR/Workbench from a release previous to Release 4.0.

## Contacting Customer Support

If you need assistance, contact Infogix Customer Support.

Support Phone: +1.630.505.1890

Support Email: [support@infogix.com](mailto:support@infogix.com)

Support Website: <http://support.infogix.com>

Fax Number: +1.630.505.1883

Visit our Website: [www.infogix.com](http://www.infogix.com)

---

# Installing ACR/Summary and ACR/Detail Server

This chapter provides directions for installing ACR/Summary and ACR/Detail Server. It contains the following sections:

- “System Requirements for the Server” on page 7
- “Overview of Server and Client Installation and Setup Steps” on page 7
- “Installing the Product” on page 8
- “Increase the Maximum File Size (Optional)” on page 10
- “Setting Up Java and COBOL Environment (Optional)” on page 10
- “Licensing Key” on page 11

## System Requirements for the Server

Contact Infogix Support to get information about the minimum system requirements for the ACR/Summary and ACR/Detail Server.

## Overview of Server and Client Installation and Setup Steps

The steps for installation and setup of the ACR/Summary and ACR/Detail Server and Client(s) are as follows. Where additional detail is needed, the steps provide references to the appropriate sections.

1. Before installing the server, do the following:
  - Ensure that you the ACR/Summary and ACR/Detail Server installers.
  - Ensure that you have administrator rights for the system where you will install ACR/Summary and ACR/Detail Server.
  - Verify that the system where you plan to install the server meets the requirements described in the next section.
  - Determine whether you will use dual install, as described in the next step.

## 2 ■ Installing ACR/Summary and ACR/Detail Server

---

### *Installing the Product*

2. If you are upgrading from a previous release, uninstall the old release only if appropriate:
  - If you want to install and test the new release of the Server while continuing to support the old release (this is called a dual install), do not uninstall the old release.
  - If you do not want to perform a dual install, stop the service on the Server Properties dialog box and uninstall ACR/Summary and ACR/Detail Server using the **Add or Remove Programs** option on the Control Panel.
3. Run **iACRSumDet Server.exe** and follow the wizard prompts (see “Installing the Product” on page 8).
4. Increase the maximum file size if appropriate (see “Increase the Maximum File Size (Optional)” on page 10).
5. If this is the first installation of ACR/Summary and ACR/Detail Server, install the licensing key (see “Licensing Key” on page 11).
6. If this is the first installation of ACR/Summary and ACR/Detail Server, create a New User account for the Server that will be used to log on to the service, start and stop the Server, configure the Server, and activate and maintain the licensing (see “Creating a Logon Account” on page 13).
7. Set up or modify properties of the Server in the Server Properties dialog box (see “Setting and Modifying Server Properties” on page 17.)
8. Implement or update your licensing as appropriate. See “Implementing and Maintaining Your Licensing” on page 22.
9. If you are upgrading from a release previous to Release 4.0, you must follow the instructions for your product in “Upgrading from a Pre-Release 4.0 Release” on page 39.
10. If you are installing an upgrade, uninstall existing clients using the **Add or Remove Programs** option on the Control Panel.
11. Install the ACR/Summary Client and/or ACR/Detail Client on user PCs (see “Steps for Installing a Client” on page 31).

## Installing the Product

---

**Note:** Before you begin, review the “Overview of Server and Client Installation and Setup Steps” above. Ensure that you have uninstalled the previous release only if you do not want to use the dual install feature described in step 2 on page 8.

---

1. Run **iACRSumDet Server.exe** program to install the product.
2. On the Welcome page, click **Next**.
3. On the Select Destination Directory page, accept the default installation directory, or browse for the directory you prefer.  
The default installation path is: **C:\Infogix\SumDetServer**.
4. Click **Next**.
5. On the Communication Parameters page, accept the defaults for the administration and user port numbers, or enter the port numbers that apply in your environment.

The **Administration port number** is used for starting and stopping the ACR/Summary and ACR/Detail Server.

The **User port number** is used by the clients to communicate requests to the server for ACR/Summary and ACR/Detail services. Some examples of ACR/Summary services are updating the definition database and performing balancing. ACR/Detail services include updating the definition database and performing reconciliation

---

**Note:** The user port number you enter here must also be entered in the Add/Edit Configuration dialog box of the ACR/Summary and/or ACR/Detail Client on the user's PC.

---

Typically, the default port numbers are not in use by any common protocol such as FTP, SMTP, SNMP, or HTTP. However, another software product installed on your system may use these ports. If this is the case, you will need to select different port numbers that are not already assigned to another service.

The Administrative and User Port numbers must be different. For instance, you cannot enter 3000 for both. Valid port numbers are between 1 and 65535.

6. Click **Next**.
7. On the Log File Options page, if you want the ACR/Summary and ACR/Detail Server to log the processing messages that it issues, make sure that the **Write messages to log file** check box is marked.  
By default, the ACR/Summary and ACR/Detail Server will log messages in the **SumDetSv.log** file. The log file will be located in the same folder where the ACR/Summary and ACR/Detail Server is installed. If you prefer to save the log file in a different folder, click **Browse**. Messages will be retained in the log file for 30 days, unless you specify a different time period.

## 2 ■ Installing ACR/Summary and ACR/Detail Server

---

### *Increase the Maximum File Size (Optional)*

8. Click **Next** to review the installation parameters.
9. If you are satisfied with the information shown, click **Next** to perform the installation.  
Otherwise, click **Back** to go back to previous pages so you can change the installation parameters. You can also change settings for the Communication and Logging parameters after installation through the Server Properties dialog box. See “[Setting and Modifying Server Properties](#)” on page 17.
10. When the Installation Completed page appears, click **Finish** to complete the installation.
11. If you are prompted to restart the computer, click **OK** in the Install dialog box. Otherwise, restart your computer after you have completed [Chapter 3, “Configuring and Licensing the Server.”](#)  
You can now proceed to the next section, “[Licensing Key.](#)”

## Increase the Maximum File Size (Optional)

ACR/Summary and ACR/Detail ship with environment variable FILEMAXSIZE=4. This setting will be appropriate for users who always use a file input size of 4GB or less. If you use input files greater than 4GB, you will have to override this value by setting FILEMAXSIZE=8 (no limit) in the extfh configuration file.

To override the environment variable FILEMAXSIZE, create the file extfh.cfg, and add the following two lines:

```
[XFH-DEFAULT]  
FILEMAXSIZE=8
```

Then, modify the batch run .skl or .bat file to set the new variable. Add a line after the SET COBCPY= command line:

For ACR/Detail, add:

```
SET EXTFH=C:\Infogix\Detail32\extfh.cfg
```

For ACR/Summary, add:

```
SET EXTFH=C:\Infogix\Summary32\extfh.cfg
```

## Setting Up Java and COBOL Environment (Optional)

To retrieve Infogix Assure history, you can use the ACR/Summary’s Infogix Assure History retrieval feature.

Infogix Assure provides a web service for the history retrieval. A Java Virtual Machine (JVM) provides the necessary run-time environment to execute Java based applications or web services.

To execute a Java based web service, set the following environment variables for COBOL and Java run-time systems:

Environment Variable	Description
<b>PATH</b>	<p>A 32-bit Amazon Corretto Java run-time system <b>jvm.dll</b> file must be available on your machine. The location of the file depends on the JDK version. You must add the file location to the system PATH variable.</p> <p>For example:</p> <pre>SET PATH=jdk-install-directory\bin\subdirectory;%PATH%</pre>
<b>CLASSPATH</b>	<p>To provide access to Java classes that are interfaced to a COBOL run-time system, add the <b>WebServiceGateway.jar</b> file location to the CLASSPATH environment variable.</p> <p>For example:</p> <pre>SET CLASSPATH=C:\Infogix\SumDetServer\Cobol\WebServiceGateway.jar;%classpath%</pre>

## Licensing Key

The compilers used by ACR/Summary and ACR/Detail on Windows and Unix/Linux platforms have been updated in ACR 9.4.

You will have to install the new license using the Micro Focus License Manager. Please contact Infogix Support prior to the upgrade to get the license file.

## 2 ■ Installing ACR/Summary and ACR/Detail Server

---

### *Licensing Key*

If this is the first installation of an ACR/Summary and ACR/Detail Server after upgrading from ACR release 9.3 or before, you must install the licensing key. If you know the proper licensing key is already installed, skip this section.

---

**Note:** After the licensing key is installed, you will still need to implement and maintain your licensing. Instructions will be provided in the next chapter in the section [Implementing and Maintaining Your Licensing](#) on page 22.

---

To install the licensing key, do the following:

1. The installer to install the license manager is included in the product installation files. Use `lmsetupx86.msi` for ACR 32-bit version, or `lmsetupx64.msi` for ACR 64-bit product version.
2. Run as administrator, `lmsetupx86.msi` for ACR 32-bit version, or `lmsetupx64.msi` for ACR 64-bit product version.
3. Click “Next” by accepting the default values in the subsequent screens in the wizard.
4. Launch “License Administration” from Windows Start Menu > Micro Focus License Manager
5. In the Install tab, click Browse. Select the license file provided by Infogix Support.
6. Select “Install Licenses” to install the license.

---

## Configuring and Licensing the Server

This chapter provides instructions for configuring and licensing ACR/Summary Server and ACR/Detail Server. It contains the following sections:

- “When You Do Not Have to Create a Logon Account” on page 13
- “Creating a Logon Account” on page 13
- “Starting the Service” on page 15
- “Setting and Modifying Server Properties” on page 17
- “Implementing and Maintaining Your Licensing” on page 22
- “Upgrading from a Pre-Release 4.0 Release” on page 30

---

**Note:** If you are upgrading from a release previous to Release 4.0, after you complete the steps in this chapter, you must follow the instructions for your product in *Upgrading from a Pre-Release 4.0 Release* on page 39.

---

### When You Do Not Have to Create a Logon Account

You do not have to create a logon account for the server in the following situations:

- You are upgrading to a new release and have already created a user account.
- You already have an account that has the appropriate level of administrative privileges and access to other network directories.

### Creating a Logon Account


Create a new user logon account as follows:

1. Select **Start**.
2. Do one of the following:

### 3 ■ Configuring and Licensing the Server

#### Creating a Logon Account

- On Windows 7, select **Start > Control Panel > Administrative Tools**. If you do not see **Administrative Tools** in the Control Panel icons, above the right corner of the list, select **View by > Small icons**.
  - On Windows Server 2008 or Windows Server 2012, select **Start > Administrative Tools**.
3. Navigate to **Computer Management > Local Users and Groups > Users**.
  4. Highlight **Users**, and select **New User**.
  5. When the New User dialog box displays, create it following the instructions below.



- a. Enter the **User name**, **Full name**, and **Description** fields. You can copy the names and description shown New User dialog box sample above or use your own.
- b. Enter a **Password**.


---

**Note:** If input files for ACR/Summary or ACR/Detail jobs reside elsewhere on your network, make sure the username and password you specify are authorized to access the directories where those files reside.

---

- c. Disable the **User Must Change Password at Next Logon** option.
- d. Enable the **Password Never Expires** option.

6. Click **Create** > **Close** to return to the previous window.
7. In the Local Users and Groups window, select **Users** to display the Select Groups window.
8. In the Select Groups window, enter **Administrators** in the object names area text box. (The contents of **From this location** will vary depending on your Windows version.)



9. Click the **Check Names** button to display the full object name.
10. Click **OK** to accept. Click **OK** again to create the account. The Member Of tab shows that the ACR/Summary and ACR/Detail Server is a member of the Administrators and Users groups. If appropriate, you can also make the account a member of additional groups.

To start the service, go to the next section.


## Starting the Service

1. From the Control Panel, select **Administrative Tools** > **Services** > **ACR SumDet Server x.x**, where x.x represents the release number. Including the release number in the service name allows you to install multiple releases on the same machine.
2. When the Properties dialog box displays, click the **Log On** tab.
  - a. For **Log on as**, select This account.

### 3 ■ Configuring and Licensing the Server

#### Starting the Service

3. Enter the ACR/Summary and ACR/Detail account you created. (If you did not create a new user account, enter an account name that has the appropriate level of administrative privileges and access to other network directories.) Or click **Browse** to open the Select User dialog box. (The contents of **From this location** will vary depending on your Windows version.)



4. If you use the Select User dialog box, click the **Check Names** button to display the full account name. Then click **OK** to close and return to the Properties dialog box (Log On tab.)
5. Type in the account's **Password**. You need to do this, even though the asterisks in the Password field make it look like a password has already been entered.
6. On the **General** tab, change the Startup type to **Automatic** if you want the ACR/Summary and ACR/Detail Server to automatically start up each time you reboot. Otherwise, whenever you reboot, you will have to start the server from the Services dialog box.

---

**Note:** The folder names for the path listed in **Path to executable** are truncated to eight characters. The full name of this path is:

**C:\Infogix\SumDetServer\sumdetsv.exe**

---

7. Click **Start** > **OK**. The ACR/Summary and ACR/Detail Server is now ready to process requests from an ACR/Summary client or the ACR/Detail client. Review the information on [“Setting and Modifying Server Properties” on page 17](#) to verify the default settings or establish settings for e-mail notification or an ACR/Connector configuration.

## Setting and Modifying Server Properties

Once you have created a logon account, you can set up and modify properties of the ACR/Summary and ACR/Detail Server in the Server Properties dialog box. Properties include communications, e-mail notification, message logging, and runtime options, as well as the licensing Control File. Some of these properties are set during installation of the server, while others can only be specified in the Server Properties dialog box. For example, if you want to select an ACR/Connector configuration or activate the e-mail notification feature, you must specify the appropriate settings in the properties dialog box.

To display the ACR/Summary and ACR/Detail Server Properties dialog box, select the **ACR SumDet Server x.x** icon (where x.x represents the release number) on the Control Panel. The upcoming sections describe the properties on each tab.

---

**Note:** **64-bit systems:** If you are running the server on a 64-bit system, the **ACR SumDet Server x.x** icon does not appear on the Control Panel. Instead, Windows redirects all 32-bit applications to another location. To set the server properties, open ACRPlusCplx.cpl (ACR/Summary and ACR/Detail Server Properties application) in the appropriate 32-bit SysWOW64 folder (C:\WINDOWS\SysWOW64).


---

### 3 ■ Configuring and Licensing the Server

#### Setting and Modifying Server Properties

## Communications

The Communications tab shows port number settings and optional ACR/Connector configuration selection.



The **User port number** and **Administration port number** display the Communication Parameters established during installation, as described in [step 5 on page 9](#). The example above shows the default port numbers that are generally used. If it is necessary to change the port numbers due to a conflict with some other software, click **Help** for details.

If your ACR/Summary or ACR/Detail installation includes ACR/Connector, select the configuration name to enable. Do not select an ACR/Connector configuration unless you want to activate ACR/Connector for all jobs running on the server.


Keep in mind that the ACR/Connector IN/Sync feature lets ACR/Connector launch other applications on other platforms (such as the mainframe) depending on the outcome of specific ACR/Summary or ACR/Detail jobs. This is desirable when jobs are running in production on the ACR/Summary and ACR/Detail Server. For example, suppose your organization has a system that can issue pager messages. You might have IN/Sync tell the paging system to send a pager message whenever a particular job issues a return code corresponding to a specified out-of-balance condition.

When users are setting up and testing ACR/Summary or ACR/Detail jobs, they probably won't want IN/Sync to launch other applications based on the jobs' outcomes. In the example above, it would be annoying for a supervisor to receive a pager message each time a test job was out of balance. This could happen if IN/Sync was set up to trigger a pager message for a production job that had the same name and issued the same return code as a test job.

If you are using ACR/Connector, the best way to avoid unexpected results may be to set up two ACR/Summary and ACR/Detail Server installations—one for testing and one for production. Then, implement the IN/Sync feature on the production server, but not on the test server. Users can switch from testing to production by running their jobs on the appropriate server. For more information, see the ACR/Connector Installation and User Guide.

## Message Logging

The Message Logging tab displays the Log File Options established during installation, as described in [step 7 on page 9](#). Messages are automatically deleted from the log after the set number of days. The **Purge now** button enables you to delete all the log entries at any time. Click **Help** for details.




### 3 ■ Configuring and Licensing the Server

#### *Setting and Modifying Server Properties*

---

## E-mail Notification

To activate the ACR/Summary and ACR/Detail e-mail notification feature, specify the host name/address and port number of your SMTP Internet mail server. Click **Help** for details.




The screenshot shows a dialog box titled "ACR/Summary and ACR/Detail Server Properties". It has a tabbed interface with five tabs: "Communications", "Message Logging", "Email Notification", "Runtime Options", and "Control File". The "Email Notification" tab is selected. Inside this tab, there are two input fields: "SMTP host name/address:" followed by an empty text box, and "SMTP port number:" followed by a text box containing the number "25". At the bottom of the dialog, there are four buttons: "OK", "Cancel", "Apply", and "Help".

For **SMTP host name/address**, enter the host name or IP address of your Internet mail server. For **SMTP port number**, accept 25 unless your mail server has a different port number.

Once you specify this information, ACR/Summary and ACR/Detail jobs that run on the server will be able to issue e-mail messages when they are out of balance. The user specifies the message to send and the e-mail address where the message should be sent. The message and e-mail address are specified in the Messages dialog box of ACR/Detail or the Direct Messages dialog box of ACR/Summary.

## Runtime Options

The Runtime Options tab should keep the default setting of +S5–NO for the **Run-time switch**. Do not change this setting unless told to do so by Customer Support.




## 3 ■ Configuring and Licensing the Server

### *Implementing and Maintaining Your Licensing*

#### Control File

The Control File tab is documented in the following section on "[Implementing and Maintaining Your Licensing](#)". Use the Control File tab to activate or update your product license.



## Implementing and Maintaining Your Licensing

The ACR/Summary and ACR/Detail Server includes a Control File that enables and controls access to your product in accordance with your license agreement. This section shows you how to do the following:

- Update your Control File.
- Generate the TM Aggregate Transaction Report, if requested.

### Updating a Control File

There are several situations when you need to perform this update. The most common include:

- When you install the ACR/Summary and ACR/Detail Server for the first time.
- When the terms of your license have changed.
- When your license for ACR/Summary and ACR/Detail is about to expire, as indicated by warning or error messages in your SYSOUT.

- When you want to run the product(s) on a machine with a host name that is not currently included in your license.

#### **Generating the Licensing Report(s)**

To generate the Product Report (file name UNI10PR.RPT), install and open the ACR/Summary and ACR/Detail Server and select the Control File tab from the server properties dialog box.

1. Complete the **Control File** field with the fully qualified name of the Control File specified during installation. To browse for the Control File (acrcntl.dat), click the button next to the field.

For example, if you accepted the default location during installation, the fully qualified name is:

```
C:\Infogix\SumDetServer\Cobol\acrcntl.dat
```

2. Select **Control File Utilities**.
3. Click **Print**.

The following report(s) will display in a new window:

- The Product Report (UNI10PR.RPT) displays the current licensing information from the Control File.
- If the Control File has ever included Transactional Measurement (TM) licensing, a Transactional Measurement Report (UNI10PRA.RPT) will be generated.

---

**Note:** If the TM column in the Product Report has the value of N (No), the TM licensing shown in the Transactional Measurement Report for that product is not currently in effect.

---

### 3 ■ Configuring and Licensing the Server

#### Implementing and Maintaining Your Licensing

#### 4. Click **Print** to print the report(s).

Following are examples of each report.

#### Product Report (UNI10PR.RPT)

```

releasenumber      PRODUCT REPORT  COPYRIGHT INFOGIX, INC.
DATE: 03042                PAGE: 1
TIME: 13:21                REPORT:  UNI10PR

FILENAME: "C:\Infogix\SumDetServer\Cobol\Acrctl.dat"
CUSTOMER:  INFOGIX, INCORPORATED
PAGE:060  WAIT:0900  RES:Y  I-RET:0000  W-RET:0000  E-RET:4000  UPDATE:004

PRODUCT  EXP  GRACE AUTH  TYPE TM  MODEL ID  HOSTNAME
U/SUM    99/999  7  ALL      H  N
                                001234X86X
                                111111/111122222222222233333333333344444444444455555555556666666666
                                33333344444
                                55555566666
                                77777788888
                                99999900000
                                22222244444
                                22222211111

VIOLATION:  FIRST DATE  LAST DATE  HOSTNAME  TYPE
              00/000    00/000
              HARDWARE
    
```

#### Transactional Measurement Report (UNI10PRA.RPT)

```

releasenumber      TRANSACTIONAL MEASUREMENT REPORT  COPYRIGHT INFOGIX, INC.
DATE: mm/dd/yy                PAGE: 01
TIME: 15:20                REPORT:  UNI10PRA

CUSTOMER:  Infogix, INCORPORATED
PAGE:060  WAIT:0900  RES:Y  I-RET:0000  W-RET:0000  E-RET:4000  UPDATE:002

-----LICENSE-----
PRODUCT TM  IND  VALUE  GRACE  RESET  VALUE
U/SUM  RULD EXEC
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST  VALUE  COUNT
03/135 03/135  5,050  3
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST  MAXIMUM VALUE  TOTAL
03/010 03/135  5,100  50

-----LICENSE-----
PRODUCT TM  IND  VALUE  GRACE  RESET  VALUE
U/SUM  RULM EXEC
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST  VALUE  COUNT
00/000 00/000  0  0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST  MAXIMUM VALUE  TOTAL
00/000 00/000  0  0

-----LICENSE-----
PRODUCT TM  IND  VALUE  GRACE  RESET  VALUE
U/SUM  RECD EXEC
-----VIOLATION PER LICENSE INTERVAL-----
FIRST  LAST  VALUE  COUNT
00/000 00/000  0  0
-----VIOLATION PER CHANGE OF LICENSE VALUE-----
FIRST  LAST  MAXIMUM VALUE  TOTAL
00/000 00/000  0  0

(Actual report may show information for additional TM types
and additional products.)
    
```

#### 5. Request your control cards and password.


Using the information in “[Contacting Customer Support](#)” on page 6, do the following:

- a. Call Customer Support to advise that you are updating the Control File according to your license agreement. Be ready to provide the reason for the update and the scheduled date.
- b. E-mail or fax the report(s) generated in the previous step to Customer Support. Mention any special considerations. For example, inform Customer Support if you are upgrading to a new release or upgrading a CPU. You will receive an e-mail or fax containing your control cards and password.

### Performing the Update

After receiving the fax or e-mail containing the control card(s) and password, complete the following steps:

1. Open the ACR/Summary and ACR/Detail Server and select the Control File tab, shown below.



2. In the **Control File** field, enter the fully qualified name of the Control File you are updating. The full name of the path shown above for the Control File is:


C:\Infogix\SumDetServer\Cobol\ACRCNTL.DAT

3. Click **Update**. The Update Control File dialog box displays an empty Control Cards text box.

### 3 ■ Configuring and Licensing the Server

#### *Implementing and Maintaining Your Licensing*

4. Type or paste the control cards and password from the fax or e-mail into the Control Cards area. Below is an example completed control card information:



5. Click **OK**.

The Control File Update (UNIFAX50.RPT) report will be displayed in a new window. Click **Print** if you want to print the report.

Following is an example of the report.

```
CHANGE ID: 11111222202351003
UNICF:  UNI.REL33.UNICF
ACCEPTED  USUM3 CT 7761  C
ACCEPTED  USUM3CCL 6805 AAAAAAAAA MF3000L2 0000 0308
ACCEPTED  USUM3CCA 2836 A S
ACCEPTED  USUM3CCE 7600 03150 04150
ACCEPTED  USUM3CCG 8666 03 30
ACCEPTED  PW 6947 JQQJQQJQQJ 673720
*****REQUEST PHASE COMPLETE*****
CHANGED  USUM3 CT 1677  C
CHANGED  USUM3CCL 5086 AAAAAAAAA MF3000L2 0000 0308
CHANGED  USUM3CCA 6382 A S
CHANGED  USUM3CCE 0067 03150 04150
CHANGED  USUM3CCG 6668 03 30
UPDATE COMPLETE
```

6. Verify the update by reviewing the UNIFAX50.RPT. If the update completed successfully, the report should contain the message **UPDATE COMPLETE**. If the report shows that any of the control cards failed, print and fax or e-mail the report to Customer Support for assistance.

## Generating the TM Aggregate Transaction Report


The TM Aggregate Transaction Report is an encrypted report that you may be requested to run by a member of the Customer Development and/or Market Development team. The report prints aggregate counts for each transaction type that is being tracked. Transaction types can include jobs, input sources, records, and rules. After you e-mail the report to the requestor at Infogix, it is decrypted and used for the following purposes:

- To aid in analyzing your transaction usage.
- To implement actual transaction usage licensing where you are billed on a “pay as you go” basis.

Follow the steps below to generate the report from the Control File.

1. Open the ACR/Summary and ACR/Detail Server and select the **Aggregate Transaction Report Utilities** button on the Control File tab.
2. Click **Print** or **Print and Reset**, depending on whether or not you want to reset the transaction counts. In either case, the Print Aggregate Transaction Report dialog box appears.

The Control Cards text box is blank until you enter one of the options described in the next steps.



### 3 ■ Configuring and Licensing the Server

#### *Implementing and Maintaining Your Licensing*

3. If you selected Print, enter one of the following options in the Control Cards text box. Otherwise skip to step 4. (Entries should be made on the first line only, starting at the left end of the line.)

Option	Purpose
<b>ALL P</b>	Print the aggregate counts for both ACR/Summary and ACR/Detail. (Leave one space between <b>ALL</b> and <b>P</b> .)
<b>USUMP</b>	Print the aggregate counts for ACR/Summary only.
<b>UDRSP</b>	Print the aggregate counts for ACR/Detail only.

4. If you selected **Print and Reset**, enter one of the following options in the Control Cards text box. Entries should be made on the first line only, starting at the left end of the line.

Option	Purpose
<b>ALL R</b>	Print the aggregate counts and reset the counters for both ACR/Summary and ACR/Detail. (Leave one space between <b>ALL</b> and <b>R</b> .)
<b>USUMR</b>	Print the aggregate counts and reset the counters for ACR/Summary only.
<b>UDRSR</b>	Print the aggregate counts and reset the counters for ACR/Detail only.

5. When you click **OK**, the aggregate report displays in a new window. The report name is UNITMPRT.RPT for the print version and UNITMRST.RPT for the print and reset version.  
If you examine the report file, the contents will be encrypted as in the following example:

```
1C:\Infogix\ACRServer\          Infogix, INCORPORATED
02CFLNFGHIJABCDEFGHIJABDDEFGHIJABCDEFGHIJBBCDEFGHIJABCDEFMHJABCDEFGHIJABCDEFHH
02FKMEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJABCDEFGHIJ
```

6. If you are going to fax the report to the requestor at Infogix, click **Print** to print the report.
7. Fax or e-mail the report to the person who requested it.

### More About the Entry Format for the Aggregate Transaction Report Dialog Box

The information in the preceding section provides all you need to generate a Transaction Measurement (TM) Report. The following information provides additional detail about the Print Aggregate Transaction Report dialog box that displays when you select Aggregate Transaction Management Utilities option on the Control File tab of the Server Properties dialog box. This information will be helpful if you expand TM licensing to additional products in the future.

Although the Print Aggregate Transaction Report dialog box initially displays blank, it requires information to be in the format described below. Information should only be entered on the first line.

The following graphic shows the left end of the dialog box.

1	2	3	4	5
12345678901234567890123456789012345678901234567890				
PPPP	PPPP	PPPP	PPPP	PPPP

**PPPP** is repeated 16 times on the line. (The entire line is not shown here.) To allow TM licensing for additional products in the future, a total of 16 products can be specified using the **PPPP** format.

The first four characters in the positions **PPPP** at the left end of the line specify the product name. Valid entries are as follows:

- **ALL** (followed by a space to extend the entry to four characters) indicates that aggregate counts will be included for each product in the Control File for which TM aggregate counts exist.
- **USUM** indicates that aggregate counts will be included for ACR/Summary only.
- **UDRS** indicates that aggregate counts will be included for ACR/Detail only.

---

**Note:** The product name must match the information in the your Control File.

---

The fifth character is entered in the position **O** at the left end of the line and is used to specify the process option, as follows:

- **P** specifies the Print Only option.
- **R** specifies the Print and Reset option.

## Upgrading from a Pre-Release 4.0 Release

If you are upgrading from a pre-Release 4.0 release, go to “[Upgrading from a Pre-Release 4.0 Release](#)” on page 39.

---

## Installing a Client

This chapter provides the system requirements and instructions for installing ACR/Summary Client or ACR/Detail Client. It contains the following sections:

- “Before You Begin” on page 31
- “System Requirements for a Client” on page 31
- “Steps for Installing a Client” on page 31

### Before You Begin

Before you begin installation, do the following:

- Verify that the system where you plan to install the client meets the requirements described in “System Requirements for a Client” on page 31.
- Arrange for network access to ACR/Summary and ACR/Detail Server.

### System Requirements for a Client

Contact Infogix Support to get information about the minimum system requirements for the ACR/Summary and ACR/Detail clients.

### Steps for Installing a Client

1. From the PC where you will install the client, select the appropriate setup program on the ACR/Summary and ACR/Detail x.x Server (where x.x represents the release number):
  - **SetupSum.exe** for ACR/Summary Client
  - **SetupDet.exe** for ACR/Detail ClientThe program is normally in the server’s Infogix\SumDetServer\Client directory.
2. The installation wizard will prompt you through the process. When the process completes, the ACR/Summary Client or the ACR/Detail Client will be installed in the Infogix program group, unless you specified a different installation directory.

## 4 ■ Installing a Client

---

### *Steps for Installing a Client*

3. If you have both clients, repeat the installation process for the remaining product.

Following installation, see the appropriate user guide for instructions on accessing, configuring and using the clients:

- *ACR/Summary User Guide for Windows and UNIX*
- *ACR/Detail User Guide for Windows and UNIX*

---

# Installing and Licensing ACR/ Workbench

If you purchased the ACR/Workbench for Summary or ACR/Workbench for Detail, this chapter provides the installation and licensing instructions.

This chapter contains the following sections:

- “System Requirements for ACR/Workbench” on page 33
- “Overview of ACR/Workbench Installation and Setup Steps” on page 33
- “Uninstall the Previous Release if Appropriate” on page 33
- “Installing the Product” on page 34
- “Installing the Licensing Key” on page 34
- “Upgrading from a Pre-Release 4.0 Release” on page 36
- “Setting Up Java and COBOL Environment (Optional)” on page 36
- “Using ACR/Workbench” on page 37

## System Requirements for ACR/Workbench

Contact Infogix Support to get information about the minimum system requirements for ACR/Workbench for Summary or ACR/Workbench for Detail.

## Overview of ACR/Workbench Installation and Setup Steps

This section summarizes the steps for installation and setup of ACR/Workbench for Summary or ACR/Workbench for Detail. Consult the next sections in order to perform the steps.

## Uninstall the Previous Release if Appropriate

If you are upgrading from a previous release, uninstall the old release only if appropriate, as explained below:

## 5 ■ Installing and Licensing ACR/Workbench

---

### *Installing the Product*

- If you want to install and test the new release of ACR/Workbench while continuing to support the old release (this is called a dual install), do not uninstall the old release.
- If you do not want to use the dual install feature, uninstall the previous version of ACR/Workbench using the **Add or Remove Programs** option on the Control Panel.

## Installing the Product

---

**Note:** Before you begin, review “[Uninstall the Previous Release if Appropriate](#)” above. Ensure that you have uninstalled the previous release only if you do not want to use dual install.

---

1. Run **iSummaryWB.exe** to install ACR/Summary Workbench, or run **iDetailWB64.exe** to install ACR/Detail Workbench.
2. Follow the prompts through the installation process.  
The program will install the product in the one of the following unless you specify a different installation directory:

C:\Infogix\Detail32  
C:\Infogix\Summary32

## Installing the Licensing Key

When you install ACR/Workbench for the first time, a Micro Focus licensing key is required to properly run ACR/Summary or ACR/Detail jobs. If you install both products, you only need to install the key once. Instructions for installing the key are provided below.

---

**Note:** The compilers used by ACR/Summary and ACR/Detail on Windows and Unix/Linux platforms have been updated in ACR 9.4.

You will have to install the new license using the Micro Focus License Manager. Please contact Infogix Support prior to the upgrade to get the license file.

If this is the first installation of ACR/Summary and ACR/Detail Server after upgrading from ACR release 9.3 or before, you must install the licensing key. If you know the proper licensing key is already installed, skip this section.

---

To install the licensing key, do the following:

1. The installer to install the license manager is included in the product installation files. Use `lmsetupx86.msi` for ACR 32-bit version, or `lmsetupx64.msi` for ACR 64-bit product version.
2. Run as administrator, `lmsetupx86.msi` for ACR 32-bit version, or `lmsetupx64.msi` for ACR 64-bit product version.
3. Click “Next” by accepting the default values in the subsequent screens in the wizard.
4. Launch “License Administration” from Windows Start Menu > Micro Focus License Manager
5. In the Install tab, click Browse. Select the license file provided by Infogix Support.
6. Select “Install Licenses” to install the license.

## Upgrading from ACR 4.7, 4.8, or 4.9 Release

If you are upgrading from a release prior to Release 9.0, after you complete the relevant steps in this chapter, you must follow these instructions.

**Warning:** You must run the scan program (UNIVTBL) before your Internal Translation tables have been processed and updated in ACR 9.0 format.

For Internal Translation tables, the format of the input data and its translated value is now defined during the definition of the Internal Translation table itself. The formats entered at the table level are used for all the table entries.

For tables created in Releases 4.7, 4.8, or 4.9, the data format is entered for each entry. When these tables are opened/processed in Release 9.0, the formats entered for the first row are used as the table column formats.

If the formats of the second and/or the subsequent rows are different from the first row, users have to change the data manually to make it consistent with the table column format.

In case the table column formats are not relevant for some rows of data, the table is required to be split into separate tables.

To identify if the Internal Translation tables created in Releases 4.7, 4.8, or 4.9 have mixed formats (the second and/or the subsequent rows have data formats different from the first row), a program (UNIVTBL) has been developed to scan the Definition database to produce a list of tables that have mixed formats.

## 5 ■ Installing and Licensing ACR/Workbench

---

### *Upgrading from a Pre-Release 4.0 Release*

- From your installation directory, edit SUMVERTBL.BAT for ACR/Summary on Windows. Or, edit DETVERTBL.BAT for ACR/Detail.
- Specify the path of the working directory for ACRSWB (for ACR/Summary) and ACRDWB (for ACR/Detail). This path is the working directory of the new release.
- For UNIDF variable, specify the full path and name of the existing (unmigrated) Definition Database.
- Run SUMVERTBL for ACR/Summary and DETVERTBL for ACR/Detail.
- Review the SYSOUT from this job. The SYSOUT will contain the Definition database name and a list of Internal Translation tables that have mixed formats.
- Review the content of the Internal Translation tables and make modifications as required.

For any changes made manually to the Internal Translation tables, review the referenced extraction rules to make the necessary modifications.

## Upgrading from a Pre-Release 4.0 Release

See the instructions in “Upgrading from a Pre-Release 4.0 Release” on [page 39](#).

## Setting Up Java and COBOL Environment (Optional)

To retrieve Infogix Assure history, you can use the ACR/Summary’s Infogix Assure History retrieval feature.

Infogix Assure provides a web service for the history retrieval. A Java Virtual Machine (JVM) provides the necessary run-time environment to execute Java based applications or web services.

To execute a Java based web service, set the following environment variables for COBOL and Java run-time systems:

Environment Variable	Description
<b>PATH</b>	<p>A 32-bit Amazon Corretto Java run-time system <b>jvm.dll</b> file must be available on your machine. The location of the file depends on the JDK version. You must add the file location to the system PATH variable.</p> <p>For example:</p> <pre>SET PATH=jdk-install-directory\bin\subdirectory;%PATH%</pre> <p>Where subdirectory can be a client, classic, hotspot or a server.</p>
<b>CLASSPATH</b>	<p>To provide access to Java classes that are interfaced to a COBOL run-time system, add the <b>WebServiceGateway.jar</b> file location to the CLASSPATH environment variable.</p> <p>For example:</p> <pre>SET CLASSPATH=C:\Infogix\SumDetServer\Cobol\WebServiceGateway.jar;%classpath%</pre>

## Using ACR/Workbench

Refer to one of the following guides for instructions on starting, configuring, and using ACR/Workbench.

- “Using the Workbench” appendix in *ACR/Summary User Guide for Windows and UNIX*.
- “Using the Workbench” appendix in *ACR/Detail User Guide for Windows and UNIX*.

## 5 ■ Installing and Licensing ACR/Workbench

---

*Using ACR/Workbench*

---

# Index

## Numerics

64-bit systems 12, 20, 39

## A

ACR/Connector

    configuring communications for 21

    IN/Sync feature 21

ACR/Workbench

    dual install 38

    installing 37

    installing the CD 38

    requirements 37

ACRCNTL.DAT (Control File) 28

administering the server 13

    Windows 2003 13

    Windows 7 or 2008 16

administration port number 9, 21

Aggregate Transaction Report

    entry format 32

    generating 30

    sample 31

    see Transaction Measurement Report

## C

CD

    for installing the server 9

client

    installing 36

    system requirements 35

    User port number 10, 21

communications

    activating e-mail notification 23

    Administration port number 9, 21

    for ACR/Connector 21

    User port number 10, 21

configuring the server 13

contacting Product Support

    for licensing upgrades 27

Control File

ACRCNTL.DAT 28

aggregate count print and reset options 31

aggregate count print options 31

completion report 29

contacting Product Support 27

licensing 25

tab in server properties dialog box 25

updating 28

when to update 25

Control File Update report 29

customer support 6

## D

dual install

    ACR/Workbench 38

    server 8

## E

e-mail notification (server properties) 23

## I

IN/Sync 21

installation

    of client 35, 36

    of Net Express key

        for ACR/Workbench 39

        for server 11

    of server 7

installing ACR/Workbench 38

## K

key for Net Express 11

### L

licensing 13

Control File 25

generating TM Report 29

Micro Focus Application Server

key for Net Express 11

reports 26

UNIFAX50.RPT 29

updating the Control File

performing the update 28

preparation 25

log 10

logon account for server 13

Windows 2003 13

Windows 7 or 2008 16

### M

message logging

setting during installation 10

setting through server properties 22

Micro Focus Application Server

licensing key 11

### N

Net Express licensing key 11

notification by e-mail 23

### O

operating system

requirement for ACR/Workbench 37

### P

ports

for client users 9, 21

for server administration 9, 21

Product Report (UNI10PR.RPT) 27

Product Support

contacting for Control File updates 27

### R

reports

Aggregate TM count (UNITMPRT.RPT) 31

Aggregate TM count and reset

(UNITMRST.RPT) 31

Control File Update Report

(UNIFAX50.RPT) 28, 29

for licensing control 26

Product Report (UNI10PR.RPT) 27

Transaction Management Report

(UNI10PRA.RPT) 27

reset Aggregate TM counts (Control File) 31

runtime options (server properties) 24

### S

server

Control File 25

creating logon account 13

Windows 2003 13

Windows 7 or 2008 16

dual install 8

installing 8, 9

log 10

starting 18

system requirements 7

server properties

Communications 21

configuring or modifying 20

Control File 25

Email notification 23

Message logging 22

Runtime options 24

setup.exe 38

for server 9

for server Net Express key 11

SetupDet.exe 36

SetupSum.exe 36

starting the server 18

system requirements

ACR/Workbench 37

clients 35

server 7

**T****TM**

- aggregate counts
  - for ACR/Detail, only 32
  - for ACR/Summary, only 32
  - for all 32
- Aggregate report
  - count 30
  - count and reset 30
- entry format for Aggregate Transactions 32
- field for TM in Product Report 26
- Transaction Measurement (TM) Report
  - generating 26
  - sample (UNILSTA) 27
  - see Aggregate Transaction Report
- transaction reports
  - aggregate 30
  - generated with Control File Utilities 26

**U**

- UNI10PR.RPT (Product Report) 26
- UNI10PRA.RPT (Transaction Management Report) 26
- UNIFAX50.RPT (Control Update) 29
- UNILSTA (TM Report) 27
- UNITMPRT.RPT (Aggregate TM count) 30, 31
- UNITMRST.RPT (Aggregate TM count and reset) 30, 31
- updating or modifying
  - server properties 20
- updating the Control File
  - performing the update 28
  - preparation 25
- user port number 10, 21

**W**

- Windows
  - requirements for ACR/Workbench 37
- Write messages to log file 10

